

Bar Code Setups for Symbol Model LS4208

1.0 Move from Item Product to Item Product:

The following setup procedure is for quickly scanning items on the Invoice of WMS7. It is assumed the scanner is using a USB cable from the handheld unit.

1. Insert the USB cable into an available USB port. Beeper Sequence will be heard, Low/Medium/High beeps (Power Up). **Scan the bar codes below in the following order.**
2. This bar code sets the default parameters of the scanner. Beeper Sequence will be heard, **High/Low/High/Low** beeps.



SET DEFAULTS

3. This bar code appends a carriage return. Beeper Sequence; **High/High** beeps.



SCAN OPTIONS

4. This bar code appends the data entry. Beeper Sequence; **High/High** beeps.



<DATA><SUFFIX>

5. This bar code sends the Down Arrow entry. Beeper Sequence; **High/High** beeps.



Send Down Arrow Key

6. This bar code sends the Left Arrow entry. Beeper Sequence; **High/High** beeps.



Send Left Arrow Key

7. This bar code appends the final Enter sequence. Beeper Sequence: **High/Low/High/Low** beeps (Successful program exit).



ENTER

8. This completes the bar code programming sequence for the Symbol bar code scanner. For each entry on an Invoice, with the mouse set on the Item Product entry, once an item is scanned, it will make the entry and go directly to a New Line below, ready for another item to be entered. The Quantity entry will default to 1.

1.1 Move from Item Product to Quantity:

The following setup procedure is for quickly scanning items on the Invoice of WMS7. It is assumed the scanner is using a USB cable from the handheld unit.

1. Insert the USB cable into an available USB port. Beeper Sequence will be heard, Low/Medium/High beeps (Power Up). **Scan the bar codes below in the following order.**
2. This bar code sets the default parameters of the scanner. Beeper Sequence will be heard, **High/Low/High/Low** beeps.



SET DEFAULTS

3. This bar code appends a carriage return. Beeper Sequence; **High/High** beeps.



SCAN OPTIONS

4. This bar code appends the data entry. Beeper Sequence; **High/High** beeps.



<DATA><SUFFIX>

5. This bar code sends the Down Arrow entry. Beeper Sequence; **High/High** beeps.



Send Down Arrow Key

6. This bar code sends the Left Arrow entry. Beeper Sequence; **High/High** beeps.



Send Left Arrow Key

7. This bar code sends the 2nd Left Arrow entry to move to the Qty field. Beeper Sequence; **High/High** beeps.



Send Left Arrow Key

8. This bar code appends the final Enter sequence. Beeper Sequence: **High/Low/High/Low** beeps (Successful program exit).



ENTER

9. This completes the bar code programming sequence for the Symbol bar code scanner. For each entry on an Invoice, with the mouse set on the **Item Product** entry, once an item is scanned, it will make the entry and go directly to a New Line **Qty** field. The **Quantity** entry will default to 1; you may change the quantity using the keyboard or leave it at the value 1. Press the **Enter** or **Tab** key to move the blank **Item Product** field, and then scan your next Bar Code.